



USB Flash Security Free Edition Quick Start

Before use USB Flash Security

1. Free edition can only be installed on the USB flash memory under 4G
2. This software can be installed on **ONE** USB flash memory.
3. [USB Flash Security] has 9 editions. [License]/[Capacity of USB disk]/[Number of USB drive can be installed by one PC] is different by each edition. Please confirm the difference of each edition in our homepage (<http://kashu-sd.co.jp/en>) or confirm it in the help after install this software.
4. Please acknowledge being not able to assume all responsibilities even if a direct or indirect damage is cause by using this software.

This file introduce the basic of installing security by several patterns and it is help the user who use [USB Flash Security] first time to use the function faster.

[Contents]

[Install on PC](#)

[Install on USB flash memory](#)

[Method of unlock security 1](#)

[Method of unlock security 2](#)

[Method of unlock security 3](#)

[Copy safely remove tool](#)

[Uninstall from USB flash memory](#)


[Uninstall from PC](#)

Install on PC


The name of setup is the following file name. Depending on the PC requirement ".exe" may be hidden. Run (double-click) the file to start the installation.

Edition	File name
Free Edition	UsbEnter_Setup.exe

1. Please open the compress (zip form) folder, run (double-click) the setup file. When the following screen displayed please click [Run] button. If the following screen did not display please go to the next step.




2. When User Account Control screen displayed, please click [Yes] button. If the following screen did not display please go to the next step.




3. When [Welcome to the USB Flash Security xxx Setup Wizard] display please click [Next] button.




4. When [License Article] screen display, please read the license article, and if you agree with this license article, please click the [Agree], and click [Next] button. In other cases please click [Cancel] button. (If you don't agree with license article, you are not allowed to you the software.)



5. When [Confirm Installation] display, please click [Next] button to start installation.



6. When [Installation Complete] display, please click [Close] button. If installation complete, shortcut will be created in program menu and desktop automatically.



[Back to contents](#)


Install on USB flash memory

USB flash memory will be formatted and data in the memory will be deleted by installing security to the memory, please backup your data to the other hard disk before install security.


1. After installation, please run (double-click) the shortcut created on desktop.




2. At first start screen display. A short description will display, please read it and click [OK] button. If do not need start screen display again, please check with [Don't display again]. And start screen won't display again next time.




3. If there is not any USB disk connect to the PC, the following screen will display.




4. Please plug the USB flash memory to install security. When USB flash memory display please select the USB flash memory and click [Install] button.



5. When install security, data in USB flash memory will be deleted. Please confirm the screen, if data in USB flash memory may be deleted, please click [OK]. If not, please click [Cancel] to stop installation.



6. When security setting screen display, please input password and hint and click [OK] button.




*Please input same password twice.

*Password distinguishes between upper case letters and lower case letters.


*Password will be saved in USB flash memory.

*Only [Encrypt (AES256) the "Protected area"] function is available in Details page.


7. When install confirm screen display, if you want to start installation, please click [OK] button.




8. Install software on USB flash memory. Please wait for a moment.




9. When install complete screen display, please click [Close] button.




10. autorun.inf and UsbEnter.exe will copy to USB flash memory when install complete.



- The capacity will be [0.00GB] in USB Flash Security main screen that installed on PC, if install security normally.




- The capacity will be [576KB] in property of USB drive, if install security normally.




[Back to contents](#)

Method of unlock security 1


1. Please unplug and plug USB flash memory to PC. Please show the file in USB flash memory in explorer. Please select `UsbEnter.exe` and run it.



2. When screen of release tool display, please input password set on USB flash memory and click [OK] button.



3. If screen of [Please wait] disappear without any error message, USB flash memory is unlocked and it can be used as normal.



[Back to contents](#)

Method of unlock security 2

1. Please unplug and plug USB flash memory to PC. When the screen of auto-run display, please run (double-click) release tool.




*The screen won't display if Service Pack is older than Service Pack 2 on Windows XP.

*If setting of auto-run is disabled, the screen won't display.


*Screen of auto-run will display on Windows 7, but release tool won't display in the screen.

*If screen of auto-run doesn't display, please unlock security by [Method of unlock security 1](#).

2. When screen of release tool display, please input password set on USB flash memory and click [OK] button.




3. If screen of [Please wait] disappear without any error message, USB flash memory is unlocked and it can be used as normal.



[Back to contents](#)

Method of unlock security 3

1. Please unplug and plug USB flash memory to PC. Please run explorer, and right-click the USB flash memory. Then select release tool in the menu to run it.




*The menu won't display if Service Pack is older than Service Pack 2 on Windows XP.


*Release tool won't display in the menu on Windows 7 by right-click USB flash memory in explorer.

*If release tool doesn't display in the menu which displayed right-click USB flash memory in explorer, please unlock security by [Method of unlock security 1](#).

2. When screen of release tool display, please input password set on USB flash memory and click [OK] button.



3. If screen of [Please wait] disappear without any error message, USB flash memory is unlocked and it can be used as normal.




[Back to contents](#)


Copy safely remove tool

Copy the tool (UsbExit.exe and autorun.inf) to remove USB flash memory USB from PC. safely remove function is not necessary, but we recommend using this tool, because safely remove tool has several functions for [USB Flash Security]. If you don't need this tool, please delete it.


1. Please connect the USB flash memory and unlock security.




2. Please select [Copy of Safely Remove tool] in operation menu.




3. When [Processing finished normally.] display, [Safely remove tool] has been copied to USB flash memory.



4. autorun.inf and UsbExit.exe are created on USB flash memory.



5. Run (double-click) UsbExit.exe, and the following screen will display. If click [Hide the protected area], it will hide the protected area and show the unprotected area. If click [Safely remove], USB flash memory will be removed from PC safely.




[Back to contents](#)


Uninstall from USB flash memory

Uninstall security and restore USB flash memory. It is necessary to do [Uninstall] function in operation menu for restore USB flash memory. Windows format can not restore USB flash memory. Data in USB flash memory will be deleted by do this operation, so if necessary please backup your data and do this operation.


1. Please run [USB Flash Security] installed on PC, and plug the USB flash memory installed security to PC.




2. Please select [Uninstall] in operation menu.




- All of data will be deleted when uninstall security from USB flash memory. If data is necessary, please click [Cancel], if not please click [OK].



- The following screen will display, if processing finished normally. Please click [OK] button.



- After uninstall security from USB flash memory, the full capacity will display in screen of [USB Flash Security] installed on PC.




[Back to contents](#)


Uninstall from PC

Delete this software from PC. USB flash memory can't be restored by deleting security from PC automatically. Please do [\[Uninstall from USB flash memory\]](#) before delete this software from PC for restoring USB flash memory. Please use [Add or Remove Programs] in [Control Panel] on XP and [Uninstall a Programs] in [Control Panel] on Windows Vista / 7 to uninstall it form PC. The following screen shot is uninstalling this software from Windows 7.


1. Please start Control Panel form start menu.




2. Please select [Uninstall a Program] in Control panel.



3. Please select this software in the screen of [Uninstall a Program] and click [Uninstall] button.



4. When the confirm screen display, please click [Yes] button to uninstall this software from PC.



[Back to contents](#)